




Saint-Gobain ISOVER (Finland) insulation template instructions for MagiCAD for AutoCAD

13/11/2025


Saint-Gobain ISOVER (Finland) insulation series template

Taking the template into use


1. Download the .zip file to your computer. Unzip the file to a suitable location.
2. Start MagiCAD, open the project management window, and choose *Merge project...* button



3. In the opened window choose the project (.EPJ file) from where you have saved it. Choose duct *Insulation series* and *Absorption material series* under the Ducts group and pipe *Insulation series* under Pipes group. Choose Compare data....



4. In the opened window you can see all *Insulation series* and *Absorption material series* that will be added to the current project. Choose **OK – Merge** button.



Group	Id	Code	Description	Status	Differences	Operation
Ducts/Insulation ...	000022	TECH Crimped ...	TECH Crimped ...	Does not exist		Create new (000...
Ducts/Insulation ...	000023	TECH Crimped ...	TECH Crimped ...	Does not exist		Create new (000...
Ducts/Insulation ...	000024	Climcover Roll A1	Climcover Roll A...	Does not exist		Create new (000...
Ducts/Insulation ...	000025	Climcover Roll A1	Climcover Roll A...	Does not exist		Create new (000...
Ducts/Insulation ...	000026	Climcover Roll A1	Climcover Roll A...	Does not exist		Create new (000...
Ducts/Insulation ...	000027	Climcover Roll A1	Climcover Roll A...	Does not exist		Create new (000...
Ducts/Insulation ...	000028	Climcover Slab ...	Climcover Slab ...	Does not exist		Create new (000...
Ducts/Insulation ...	000029	Climcover Slab ...	Climcover Slab ...	Does not exist		Create new (000...
Ducts/Insulation ...	000030	Climcover Slab ...	Climcover Slab ...	Does not exist		Create new (000...
Ducts/Insulation ...	000031	Climcover Slab ...	Climcover Slab ...	Does not exist		Create new (000...
Ducts/Insulation ...	000032	Climcover Slab ...	Climcover Slab ...	Does not exist		Create new (000...
Ducts/Insulation ...	000033	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000034	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000035	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000036	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000037	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000038	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000039	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000040	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000041	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000042	U Protect Wired ...	U Protect Wired ...	Does not exist		Create new (000...
Ducts/Insulation ...	000052	TECH Pipe Sect...	TECH Pipe Sect...	Does not exist		Create new (000...
Ducts/Insulation ...	000053	TECH Pipe Sect...	TECH Pipe Sect...	Does not exist		Create new (000...
Ducts/Insulation ...	000054	TECH Pipe Sect...	TECH Pipe Sect...	Does not exist		Create new (000...
Ducts/Insulation ...	000055	TECH Pipe Sect...	TECH Pipe Sect...	Does not exist		Create new (000...
Ducts/Insulation ...	000056	TECH Pipe Sect...	TECH PipeSecti...	Does not exist		Create new (000...
Ducts/Insulation ...	000057	TECH Pipe Sect...	TECH PipeSecti...	Does not exist		Create new (000...
Ducts/Insulation ...	000058	TECH Pipe Sect...	TECH PipeSecti...	Does not exist		Create new (000...
Ducts/Absorption...	000001	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000002	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000003	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000004	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000005	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000006	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000007	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000008	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...
Ducts/Absorption...	000009	CLIMLINER Sla...	CLIMLINER Sla...	Does not exist		Create new (000...

5. New series are added to the current project file and can be used in the drawing.

